



[2017-New-ExamsValid Braindump2go NS0-158 Dumps PDF 421q Offer[1-8

2017 May Version | New NS0-158 Exam Dumps with VCE and PDF Free Updated in www.Braindump2go.com Today!100% Real Exam Questions! 100% Exam Pass Guaranteed!1.|2017 Version New NS0-158 Exam Dumps (PDF & VCE) 421Q&As Download:<http://www.braindump2go.com/ns0-158.html> 2.|2017 Version New NS0-158 Exam Questions & Answers Download: <https://drive.google.com/drive/folders/0B75b5xYLjSSNUWNTQ3dmbXc1d2s?usp=sharing> QUESTION 1Click the Exhibit button. The maximum RAID group size of the RAID-DP agrgr1 shown in the exhibit is 18. You expand the aggregate by 20 disks.



How many of the new disks are used for data? A. 20B. 16C. 14D. 18 Answer: CExplanation:RAID 6 extends RAID 5 by adding another parity block; thus, it uses block-level striping with two parity blocks distributed across all member disks.Figure: Diagram of a RAID 6 setup, which is identical to RAID 5 other than the addition of a second parity block



QUESTION 2Which command prompt is displayed when a cluster named c11 is in Advanced privilege mode? A. c11::>B. c11::*>C. c11-01>D. SP c11-01> Answer: BExplanation:The following example sets the privilege level to advanced and then to admin:vs1::> set -privilege advancedWarning: These advanced commands are potentially dangerous; use them only when directed to do so by technical support.Do you wish to continue? (y or n): yvs1::*> set -privilege admin

<https://library.netapp.com/ecmdocs/ECMP1196807/html/GUID-FBB48AE8-C74D-4472-A5CD-799D46ED2E85.html> QUESTION

3You want to permanently reassign ownership of an aggregate to a node's partner.What should you do to accomplish this task? A. Reassign ownership of each disk in the aggregate to the partner node.B. Execute the storage aggregate relocation start command.C. Execute the storage failover command.D. Move all volumes on the aggregate to an aggregate that is owned by the partner.

Answer: BExplanation:To start the aggregate relocation process us the command: storage aggregate relocation start

<https://library.netapp.com/ecmdocs/ECMP1196905/html/GUID-AE98144E-002D-405D-88C5-198DC4B05F55.html> QUESTION 4

You want to use UTA2 ports for native FC LUN access.How do you accomplish this task? A. Configure the UTA2 ports as target ports with 16 Gb SFP+ transceivers.B. Configure the UTA2 ports as target ports with 10 Gb SFP+ transceiversC. Configure the UTA2 ports as initiator ports with 10 Gb SFP+ transceiversD. Configure the UTA2 ports as initiator ports with 16 Gb SFP+ transceivers Answer: DExplanation:Native Fibre Channel drives attach directly to the Fibre Channel SAN, eliminating the need for a router.NetApp uses the marketing term "UTA2" to refer to a new generation of network adapters that can be configured as either 10-Gb Ethernet and FCoE ports or as 16-Gb FC initiator or target ports.

<https://library.netapp.com/ecmdocs/ECMP1636035/html/GUID-EC0DDAAE-1178-48EF-B90D-0A7DF498F71B.html> QUESTION

5Click the Exhibit button. After logging into an SVM using the vsadmin user account, you are able to see existing volumes, but are unable to create new volumes.

```
omeganali:~> vserver show -vserver acmef01
Vserver: acmef01
Vserver Type: data
Vserver Subtype: default
Vserver UUID: dfe04ffc-9535-11e6-8bfc-00a0992e0f1
Root Volume: acmef01_root
Aggregate: sas_01
NIS Domain: -
Root Volume Security Style: ntfs
LDAP Client: -
Default Volume Language Code: C.UTF-8
Snapshot Policy: default
Comment: -
Quota Policy: default
List of Aggregates Assigned: -
Limit on Maximum Number of Volumes allowed: unlimited
Vserver Admin State: running
Vserver Operational State: ready
Vserver Role: primary
Disallowed Protocols: -
Is Vserver with Indefinite Volume: false
QoS Policy Group: -
Caching Policy Name: -
Comd Lock: false
IPspace Name: Default
Foreground Process: -

omeganali:~> security login show -vserver acmef01 -user-or-group-name vsadmin
Vserver: acmef01
-----
User/Group Name      Application      Authentication      Role Name      Acct      Is-Nvswitch
-----
vsadmin             http            password            vsadmin        no        no
vsadmin             ontap           password            vsadmin        no        no
vsadmin             ssh             password            vsadmin        no        no
3 entries were displayed.
```

Referring to the configuration shown in the exhibit, what is the problem? A. The vsadmin user is not assigned the correct application access. B. No aggregates have been assigned to the SVM. C. Aggregate SAS_01 is out of space. D. The vsadmin role does not have the create volumes privilege. Answer: D

QUESTION 6 The NVMe Express (NVMe) flash capacity is upgradeable in which two systems? (Choose two.) A. FAS9000B. FAS8200C. FAS2650D. AFF A700 Answer: AB

QUESTION 7 What is an array LUN? A. a LUN provisioned in ONTAP that is mounted by a connected host B. a LUN provisioned on third-party storage that ONTAP will use as a passthrough LUNC. C. a LUN that is used only as a part of a volume group D. a LUN provisioned on third-party storage that ONTAP will use in a RAID group Answer: A

QUESTION 8 Which two features are supported by SnapLock Enterprise but not by SnapLock Compliance? (Choose two.) A. FlexArray B. privileged delete C. NetApp Volume Encryption (NVE) D. SnapMirror Answer: BD

Explanation: Features supported by SnapLock Enterprise but not by SnapLock Compliance include: Note: Comparison table of SnapLock Enterprise and SnapLock Compliance The SnapLock Enterprise and the SnapLock Compliance features differ in terms of the options and permissions available for both the features. !!!RECOMMEND!!! 1. |2017 Version New NS0-158 Exam Dumps (PDF & VCE) 421Q&As Download: <http://www.braindump2go.com/ns0-158.html> 2. |2017 Version New NS0-158 Study Guide Video: YouTube Video: [YouTube.com/watch?v=5Dhu18qCw4Q](https://www.youtube.com/watch?v=5Dhu18qCw4Q)